
# **Installing CaseMap Server**

## **User Guide**

CaseMap® Server, Version 1.6

- System Requirements
- Installing CaseMap Server
- Installing the CaseMap Admin Console
- Installing the CaseMap SQL Import Utility
- Installing the TextMap SQL Import Utility
- Testing Installation
- Verifying Connectivity



## **CaseMap Server Installation Guide**

## © 2014 LexisNexis. All rights reserved.

No part of this work may be reproduced or transmitted in any form or by any means, electronic or mechanical, including photocopying, recording, or by any information storage or retrieval system, without permission.

While the information contained herein is believed to be accurate, this work is provided "as is," without warranty of any kind. The information contained in this work does not constitute, and is not intended as, legal advice.

Lexis Nexis and the Knowledge Burst logo are registered trademarks of Reed Elsevier Inc., used under license. Concordance is a registered trademark of Lexis Nexis, a division of Reed Elsevier Inc. Other products or services may be trademarks or registered trademarks of their respective companies.

CaseMap® DocPreviewer™ DocManager™ CaseMap® Server TextMap®

Version: CaseMap® Server 1.6, CaseMap® Admin Console 1.6, CaseMap® SQL Import Utility 1.0, TextMap® SQL Import

Utility 1.0

Release: March 14, 2011

# **Table of Contents**

Chapter	1 What's New in Version 1.6	5
Chapter	2 Installing CaseMap Server	7
1	System requirements v1.6	7
2	Installing the CaseMap Server	15
	Configuring SQL Server for CaseMap Server	15
	Configuring SQL Server Service Broker	
	Configuring SQL Server for CaseMap templates	
	Installing CaseMap Server	
	Automating the client connection with the CaseMap Server	
_	Opening SQL cases from the command line	
3		
	Installing CaseMap Admin Console	
4	Installing the CaseMap SQL Import Utility	45
	Installing the CaseMap SQL Import Utility	45
5	Installing the TextMap SQL Import Utility	52
	Installing the TextMap SQL Import Utility	52
6		
	About migrating cases	
	Migrating cases to CaseMap Server	
7		
8	•	
J	yg	
	Index	67

# **Installing CaseMap Server**

User Guide

## What's New in Version 1.6

# Chapter



## What's New in Version 1.6

## CaseMap Server v1.6

CaseMap Server v1.6 now provides the ability to set up a CaseMap SharePoint Web Part that allows you to display CaseMap case data from active SQL cases. With the CaseMap SharePoint Web Part, data is published to a central SharePoint location so staff can access and view case data without having to open a CaseMap case. Administrators can now publish case data without having to manually retrieve it from a case file.

For more information, see About CaseMap SharePoint Web Part.



About CaseMap Server
System requirements v1.6

# **Installing CaseMap Server**

User Guide

## **Installing CaseMap Server**

## Chapter

2

## **Installing CaseMap Server**

## System requirements v1.6

Please review the current system requirements for setup considerations and suggestions. Review each section in advance before making expensive hardware and network decisions that may not be in line with LexisNexis CaseMap or TextMap recommendations.

Please keep informed of CaseMap Server, CaseMap Admin Console, and CaseMap/TextMap SQL Import Utility release updates and how they impact your system by contacting your CaseMap Sales or Support Representative.

When setting up users for local cases, ensure that all users have full network access to each case directory they need to access. When setting up users for SQL cases in the CaseMap Admin Console, ensure that users are assigned appropriate roles and assigned to the case files they need access.

## **■** CaseMap Server v1.6

CaseMap Server is a Windows® .NET WCF Web service that authenticates CaseMap users and is used to store or retrieve data from the admin database. CaseMap Server must be installed on a local hard drive. You must be logged on with admin rights to install CaseMap Server

- 2 GHz or faster 32-bit (x86) or 64-bit (x64) processor
- 2 GB of RAM or greater
- Approximately 100 MB of free disk space on the system drive
- Super VGA (800 x 600) or higher-resolution monitor with 256 colors
- Any of the following versions of Microsoft Windows®:

Microsoft Windows 2003 Server®

Microsoft Windows 2008 Server®

• Any of the following versions of Microsoft Internet Information Server®

Microsoft Windows Microsoft IIS 6.0®

Microsoft Windows Microsoft IIS 7.0®

- Microsoft .NET Framework v3.5 and above
- The CaseMap Server requires CaseMap SQL case databases to reside in Microsoft SQL Server 2005, Service Pack 2 or higher, or SQL Server 2008.
- ☑ The CaseMap Server requires the TextMap admin database to reside in Microsoft SQL Server 2005 or SQL Server 2008. The installer will prompt you for SQL Server Credentials to create the admin database.
- Service Broker must be enabled in Microsoft SQL Server for databases that get created

when new TextMap SQL cases are created or registered in the CaseMap Admin Console. Enabling Service Broker ensures indexing success when transcripts are imported into a SQL case file. If Service Broker is disabled, indexing and re-indexing will not occur during import or case creation. See Configuring SQL Server Service Broker.

- ☑ The CaseMap Server should only be accessible from within the secured network and any access to the CaseMap Server from Internet should be blocked.
- The CaseMap Server runs under a service account that has privileges to perform LDAP queries against Active Directory and has read/write/execute permissions on the TextMap admin database.
- ☑ The CaseMap Server has two web services: one for the TextMap client application and the other for the CaseMap Admin Console to use.

  Admin Console Service Default URL: http://[Web\_Server\_Name]/CMServer/CMServerAdmin.svc

  Client Application Service Default URL: http://[Web\_Server\_Name]/CMServer/CMServerClient.svc

  ☐ CMServerClient.svc

  ☐ CMServ

#### **\_\_CaseMap Admin Console v1.5**

The CaseMap Admin Console is the Windows desktop application providing access to the CaseMap Server Web Service. Install the CaseMap Admin Console to the Microsoft Windows desktop of any user who will administer TextMap SQL cases and other users.

The CaseMap Admin Console must be installed and run on a local hard drive. The CaseMap Admin Console can not be run from a network server. CaseMap Admin Console data is stored on an Admin Database residing in a Microsoft® SQL Server® database. You must be logged on with Admin rights to install the CaseMap Admin Console.

- 1 GHz or faster 32-bit (x86) or 64-bit (x64) processor
- 1 GB RAM (32-bit) or 2 GB RAM (64-bit)
- Approximately 30 MB of free disk space on the system drive
- Super VGA (800 x 600) or higher-resolution monitor with 256 colors
- Any of the following versions of Microsoft Windows®:

Microsoft Windows XP Professional or Home®

Microsoft Windows 2003 Server®

Microsoft Windows 2008 Server®

Microsoft Windows Vista®

Microsoft Windows 7®

When prompted to enter URL for CaseMap Server (optional), please enter an URL ending with CMServerAdmin.svc. CaseMap Server is required to administer TextMap SQL cases and respective users.

## **■** CaseMap SQL Import Utility v1.0

The CaseMap SQL Import Utility is an administrative tool used to migrate existing case file

databases from Microsoft Access to Microsoft SQL Server. The CaseMap SQL Import Utility must be installed and run on a local hard drive. The CaseMap SQL Import Utility cannot be run from a network server. You must be logged on with admin rights to install the CaseMap SQL Import Utility.

Each CaseMap case requires a distinct SQL database. After you import an Access case into a SQL Server database, use the CaseMap Admin Console to register the case and then assign it to users.

- 1 GHz or faster 32-bit (x86) or 64-bit (x64) processor
- 1 GB RAM (32-bit) or 2 GB RAM (64-bit)
- Approximately 30 MB of free disk space on the system drive
- Super VGA (800 x 600) or higher-resolution monitor with 256 colors
- Any of the following versions of Microsoft Windows®:

Microsoft Windows XP Professional or Home®

Microsoft Windows 2003 Server®

Microsoft Windows 2008 Server®

Microsoft Windows Vista®

Microsoft Windows 7®

## **■\_TextMap SQL Import Utility v1.0**

The TextMap SQL Import Utility is an administrative tool used to migrate existing case file databases from Microsoft Access to Microsoft SQL Server. The TextMap SQL Import Utility must be installed and run on a local hard drive. TextMap SQL Import Utility cannot be run from a network server. You must be logged on with admin rights to install the TextMap SQL Import Utility.

Each TextMap case requires a distinct SQL database. After you import an Access case file into a SQL Server database, use the CaseMap Admin Console to register the case and then assign it to users.

- 1 GHz or faster 32-bit (x86) or 64-bit (x64) processor
- 1 GB RAM (32-bit) or 2 GB RAM (64-bit)
- Approximately 30 MB of free disk space on the system drive
- Super VGA (800 x 600) or higher-resolution monitor with 256 colors
- Any of the following versions of Microsoft Windows®:

Microsoft Windows XP Professional or Home®

Microsoft Windows 2003 Server®

Microsoft Windows 2008 Server®

Microsoft Windows Vista®

Microsoft Windows 7®

#### **■** Review additional recommendations


Review the following for additional information regarding recommendations.

#### **■**\_Calculating user capacity


Network connection speed, network traffic, database size, and other items may be a factor when evaluating performance. To maximize performance, the user capacity of the CaseMap Server is metered by the hardware. A Pentium CPU will support 25 users. A Xeon or Pentium Hyper Threaded (HT) CPU will support 50 users. Multiple CPU capacity for dual and quad CPU servers. Server capacity is also limited by bandwidth on your LAN and WAN, as well as file server speed.

#### **■\_Web Servers**


The CaseMap Server requires a Microsoft Internet Information Server (IIS) v6.0 or v7.0 Web server. If you are installing CaseMap Server on an IIS 6 server, you will need to ensure that aspnet\_isapi.dll is allowed.



The application pool identity must be configured for IIS by running the aspnet\_regiis utility. You can do this from the command line (running as Administrator).



It must also hold the Log On As Service right in the LSA.



The CaseMap Server should only be accessible inside your protected network and requires installation to a single Windows® Server 2003 or 2008. You should not allow access to the CaseMap Server from the Internet.

Please use standard configurations for an IIS web server. The CaseMap Server web

services will use the ports that are assigned to its parent Web site in IIS. However, CaseMap and the CaseMap Admin Console expect the CaseMap Server to be on port 80 for HTTP or 443 for SSL.

CaseMap Server supports SSL encryption. It is recommended that you require SSL connections to the CaseMap Server's parent Web site.

## ■ Configure the WebConfig file to support SSL

If the hosting web site of the CaseMap Server does not have an SSL binding in Microsoft IIS, the SSL endpoints will need to be modified.

## **■**\_To enable support for SSL

For your convenience, we have already included the necessary elements in the web.config to support SSL. However, these configuration values are commented by default. To enable support for SSL, you will need to uncomment some values in the Web.config file.

```
1. Locate the following:
   <!-- SSL Support
   <bindings>
     <basicHttpBinding>
      <br/><binding name="SecurityByTransport">
       <security mode="Transport">
        <transport clientCredentialType="None"/>
       </security>
      </binding>
     </basicHttpBinding>
   </bindings>
2. Change Step 1 to the following:
   <!-- SSL Support -->
   <br/>
<br/>
dings>
     <basicHttpBinding>
      <binding name="SecurityByTransport">
       <security mode="Transport">
```

```
<transport clientCredentialType="None"/>
        </security>
      </binding>
     </basicHttpBinding>
    </bindings>
3. Next locate the following:
    <!-- SSL Endpoint
    <endpoint address ="" binding="basicHttpBinding"</pre>
bindingConfiguration="SecurityByTransport" contract="LexisNexis.
CMServer.WebServices.ICMServerClient"/>
4. Change Step 3 to the following:
    <!-- SSL Endpoint -->
<endpoint address ="" binding="basicHttpBinding"
bindingConfiguration="SecurityByTransport" contract="LexisNexis.</pre>
CMServer.WebServices.ICMServerClient"/>
5. Now locate the following:
    <!-- SSL Endpoint
<endpoint address ="" binding="basicHttpBinding"
bindingConfiguration="SecurityByTransport" contract="LexisNexis.</pre>
CMServer.WebServices.ICMServerAdmin"/>
6. Change Step 5 to the following:
     <!-- SSL Endpoint -->
<endpoint address ="" binding="basicHttpBinding"
bindingConfiguration="SecurityByTransport" contract="LexisNexis.</pre>
CMServer.WebServices.ICMServerAdmin"/>
```

## **■** To enable support for debugging

To enable support for debugging, you will need to uncomment some values in the Web.config file.

1. Locate the following text:

```
<!-- Debugging Support
<compilation debug="true"/>
```

```
<customErrors mode="Off">
-->
```

2. Change the text in Step 1 to the following:

```
<!-- Debugging Support -->
<compilation debug="true"/>
<customErrors mode="Off">
```

#### **■\_Authentication Types**

Windows Authentication logons can be used by the CaseMap Server, making user administration easy and fully integrated with your existing network policies. CaseMap Server reuses Windows credentials to authenticate a user. Once a user logs on to Windows, CaseMap Server can use that same log on so that a user does not need to respecify their credentials.

CaseMap Server with Active Directory can be used to verify users' logons and passwords. Logons are checked with Windows Security Controller. Setting this up helps ensure conformation with password policies.

## CaseMap Server has two authentication type options:

- Windows Authentication (External by LDAP) Authentication by Lightweight Directory Access Protocol (Active Directory) for accessing SQL case files in CaseMap Server.
- **Simple Authentication** CaseMap handles authentication for accessing case files.

When using Windows Authentication, you will need to first set up users in the Active Directory and then add the user name to the CaseMap Admin Console. When using Windows authentication, it is important that user names match in both the Active Directory and the CaseMap Admin Console.

Related Topics

Installing CaseMap Admin Console

## Installing the CaseMap Server

## Configuring SQL Server for CaseMap Server

Before you install the CaseMap Server, you need to create an admin database and login account in Microsoft SQL Server.

Any time you uninstall/reinstall CaseMap Server, you will need to create a new admin database and login accounts in SQL Server Management Studio.

## **■\_To configure SQL for CaseMap Server**

- 1. Open Microsoft SQL Server.
- 2. Connect to the database engine, using a system administrator account, on the server that will contain the CaseMap Server admin database.
- 3. In **Object Explorer**, right-click on the **Databases** folder and click **New Database**.
- 4. In the **New Database** dialog box, type in the name of the admin database in the **Database Name** field, then click **OK**.
- 5. In the **Object Explorer** pane, expand the **Security** folder, and then expand the **Logins** folder.
- 6. Right-click on Logins folder and click New Login.
- 7. In the **Login New** dialog box, type in the login name in the **Login name** field.
- 8. Select the authentication type you want to use: Windows or SQL.

If you choose SQL, then type in a password and confirm it.

If you choose Windows Authentication, the login name must be the same account used for Anonymous Authentication by the CaseMap Server.

- 9. In the **Default database** field, select the admin database you created.
- 10. Click **OK** to continue.

You are now ready to install CaseMap Server.

#### Related Topics

About CaseMap Server

Installing CaseMap Server

Registering SQL Servers

Configuring SQL Server for CaseMap templates

## **Configuring SQL Server Service Broker**

Service Broker must be enabled in Microsoft® SQL Server for databases created when new TextMap SQL cases are created or registered in the CaseMap Admin Console. Enabling Service Broker ensures indexing success when transcripts are imported into a SQL case file. If Service Broker is disabled, indexing and re-indexing will not occur during import or case creation.

When new TextMap SQL cases are created, the new case will have Service Broker enabled. However, if a database administrator restores a SQL database, the restored SQL database will have Server Broker disabled. After a SQL database is restored from a backup, database administrators need to enable Service Broker for the database.

### **\_\_To check the status of Service Broker**

SELECT is\_broker\_enabled FROM sys.databases WHERE name = 'Database name'

A value of 0 indicates it is off, 1 is on.

#### **■\_To enable Service Broker**

Alter Database [DB\_NAME] Set ENABLE\_BROKER

Related Topics

Configuring SQL Server for CaseMap Server

## **Configuring SQL Server for CaseMap templates**


If you want to create CaseMap SQL cases from existing CaseMap SQL templates, you need to configure SQL Server in order for this to work successfully.

#### **■\_To configure SQL Server 2005 for CaseMap templates**

- 1. Open Microsoft SQL Server 2005.
- 2. Click Configuration Tools.
- 3. Click SQL Server Surface Area Configuration.
- 4. In the SQL Server 2005 Surface Area Configuration dialog box, click Surface Area Configuration for Features.




In the Surface Area Configuration for Features dialog box, click to expand Database engine.




- 6. Click Ad Hoc Remote Queries.
- 7. Select the **Enable OPENBROWSE and OPENDATASOURCE support** check box, then click **OK**.

#### **■\_To configure SQL Server 2008 for CaseMap templates**

- 1. Open Microsoft SQL Server Management Studio 2008.
- 2. Logon to SQL Server Server Management Studio.
- 3. In the **Object Explorer** pane, right-click on the server name (root node).



- 4. Click the **Facets** option.
- 5. In the Facet drop-down listing, click Surface Area Configuration.



- 6. In the **View Facets** box, click in the right column for **AdHocRemoteQueriesEnablednow** until it displays **True**.
- 7. Click OK.

Related Topics

Configuring SQL Server for CaseMap Server

Creating SQL cases from CaseMap templates

## **Installing CaseMap Server**

Install the CaseMap Server to Windows® Server 2003 or 2008 inside your WAN. The CaseMap Server requires a Microsoft SQL Server 2005 or 2008 admin database. Creating the admin database manually is optional. If the admin database is already created, then the installer will

configure it. Otherwise, the installer will create and configure the admin database. We recommend that you install the SQL Server admin database on a different machine than that of the Microsoft IIS web server.

## The CaseMap Server Web Service has two web services:

- CaseMap or TextMap Client (default URL) http://[Web\_Server\_Name]/CMServer/ CMServerClient.svc
- CaseMap Admin Console (default URL) http://[Web\_Server\_Name]/CMServer/ CMServerAdmin.svc
- ▲ The CaseMap Server is a collection of .NET WCF Web services that should only be available inside your WAN. You should block access to the CaseMap Server on the Internet.
- If you use Active Directory authentication for CaseMap/TextMap users, then CaseMap Server requires Microsoft Windows service account that has privileges to perform LDAP queries against Active Directory. An account without these privileges is not able to authenticate users. We recommend you set up a special account just for this purpose and assign it a permanent password.

## **■\_To install CaseMap Server**


- 1. Click on the **CMServerSetup.exe** file to launch the CaseMap Server install utility.
- 2. When the utility launches, click Next.



3. In the **License Agreement** dialog box, review the license agreement and select the **I** accept the terms in the license agreement option.



- 4. Click the **Print** button if you would like a copy of the license agreement printed at this time
- 5. Click **Next** to continue.
- 6. In the **Information** dialog box, review important installation information.



7. Click **Next** to open the **Service Account Information** dialog box.



- 8. In the **User Name** field, type in the user account for the IIS application pool.
- 9. In the **Password** field, type in the user account password.

We recommend that you set the service account password to never expire.

10. Click Next to open the Create CaseMap Server Admin Database dialog box.



- 11. In the **SQL Server that you are install to** field, type in the server name.
- 12. In the **Connect using** area, select the authentication type you are using: Windows or SQL.

If you are using SQL Authentication, type in a user name and password.

- 13. In the **SQL database name** field, type in the admin database name.
- 14. Click **Next** to open the **CaseMap Server Admin Database Connection Information** dialog box.



15. In the **Connect using** area, select the authentication type you want to use: Windows or SOI


If you are using SQL Authentication, type in a user name and password.

Refer to Step 7 in Configuring SQL for CaseMap Server.

16. Click **Next** to open the **Select the web site** dialog box.



- 17. In the **Web site** field, type in the Web site you want to use.
- 18. In the **Application name** field, type in the server name.
- 19. Click **Next** to open the **Organization Name** dialog box.



- 20. In the **Organization or firm name** field, type in the organization or firm name.
- 21. Click **Next** to continue.
- 22. In the **Destination Folder** dialog box, click **Next** to install to this folder or click **Change** to locate another directory folder.



- 23. Click to Next to continue.
- 24. In the **Ready to Install the Program** dialog box, click **Install**.



The installation wizard will install the CaseMap Server files.

25. When the **InstallShield Wizard Complete** dialog box displays, click **Finish**.



The CaseMap Server is now installed in the directory you specified.

You can now install the CaseMap Admin Console.

## Related Topics

About CaseMap Server
Configuring SQL for CaseMap Server
Installing CaseMap Admin Console

## Automating the client connection with the CaseMap Server

Using command line parameters, you can automate the log on process for CaseMap and TextMap when using Windows Authentication. The command line setup can also be used in conjunction with the option to open SQL cases. See <a href="Opening SQL cases from the command line">Opening SQL cases from the command line</a>.

When the automatic logon option is specified, the client applications will display a Connect to CaseMap Server dialog box. If the logon succeeds, an attempt is made to open a SQL case if the "SQLCaseName" and "SQLCaseID" parameters are specified, otherwise a Browse for SQL Cases dialog box displays for the user to select which assigned case to open.

If the user's CaseMap or TextMap client application is not in SQL mode or if there are no

registered CaseMap Servers, the user will not be able to connect.

If there is more than one registered CaseMap Server, then an attempt is made to use the last used server. If there is no last used server, an attempt is made to use the first server listed in alphabetical order.

## **■**\_To enter command line parameters

The following command line parameters facilitate Windows authentication for log on to the CaseMap Server.

## CaseMap

"[PATH]\CaseMap.exe" /AutoLogOn

To use this parameter in conjunction with the "SQLCaseName" or "SQLCaseID" parameters, use the following:

"[PATH]\CaseMap.exe" /SQLCaseName "[SQL\_CASE\_NAME]" /AutoLogOn

"[PATH]\CaseMap.exe" /SQLCaseID "[SQL\_CASE\_ID]" /AutoLogOn

## **TextMap**

"[PATH]\TextMap.exe" /AutoLogOn

To use this parameter in conjunction with the "SQLCaseName" or "SQLCaseID" parameters, use the following:

"[PATH]\TextMap.exe" /SQLCaseName "[SQL\_CASE\_NAME]" /AutoLogOn

"[PATH]\TextMap.exe" /SQLCaseID "[SQL\_CASE\_ID]" /AutoLogOn

Related Topics

Opening SQL cases from the command line

## Opening SQL cases from the command line

The CaseMap Server allows you to open CaseMap and TextMap SQL cases via command line support. You must first have case portal web pages set up where you can post hyperlinks to the SQL cases, in addition to any local cases or exported case data you want available such as a case issue list or cast of characters.

Case users can then create shortcuts on their desktops or save hyperlinks as Favorites in their Internet browser to open case file assigned to them. The CaseMap and TextMap applications will launch from the web portal page. You can determine options for whether the client

application splash screen displays or whether a user logon is required before the case can be opened.

When a user launches CaseMap or TextMap and passes one of these two command line parameters, the client application will wait for the user to log into the CaseMap Server. After the user logs on to the CaseMap Server, the client application then attempts to automatically open the specified case.

If the user's CaseMap client application is not in SQL mode or the user has not successfully logged into the CaseMap Server, an error message displays to notify them. Does this also apply to TextMap?

If a case user is using a trial version of CaseMap or TextMap, and does not have trial time remaining, a message displays to notify them and offers an option to activate the client application.

## **■\_To open a CaseMap SQL case from the command line**

Use the following command line format to open a CaseMap SQL Case Name or SQL Case ID:

"[PATH]\CaseMap.exe" /SQLCaseName "[SQL\_CASE\_NAME]"

"[PATH]\CaseMap.exe" /SQLCaseID "[SQL\_CASE\_ID]"

CaseMap allows the user to pass a file name as the first parameter on the command line to open the file, e.g. "CaseMap.exe C:\Program Files\Microsoft SQL\Server\MSSQL\DATA \database.mdf". The file path and name must be the first parameter in the command line.

This can also be combined with "-nosplash" and "-nodlg", and the file name must be the first parameter on the command line.

**Correct** (suppresses the splash screen and opens the case file)

"CaseMap.exe C:\Program Files\Microsoft SQL\Server\MSSQL\DATA\database.mdf -nosplash"

**Incorrect** (suppresses the splash screen, but does not open the case file)

"CaseMap.exe -nosplash C:\Program Files\Microsoft SQL\Server\MSSQL\DATA \database.mdf"

#### **■\_To open a TextMap SQL case from the command line**

Use the following command line format to open a TextMap SQL Case Name or SQL Case ID:

"[PATH]\TextMap.exe" /SQLCaseName "[SQL\_CASE\_NAME]"

"[PATH]\TextMap.exe" /SQLCaseID "[SQL\_CASE\_ID]"

Related Topics

Automating the client connection with the CaseMap Server

## Installing the CaseMap Admin Console

## **Installing CaseMap Admin Console**

The CaseMap Admin Console is the Windows desktop application providing user interface access for the CaseMap Server. Installation of the CaseMap Admin Console is fairly simple and done using an install wizard. Install the CaseMap Admin Console to the desktop of any user who will be administering CaseMap and TextMap case files and users. The CaseMap Admin Console supports both Windows and simple authentication.

The install utility will prompt you to enter the URL to the CaseMap Server. The URL should end with "CMServerAdmin.svc".

The CaseMap Server automatically creates a system administrator user with a default user name and password:

- User Name = sysadmin
- Password = password

Once you log into the CaseMap Admin Console for the first time using the sysadmin user account you can change the default password. The sysadmin password can be modified by clicking Tools > Options.

After installing the CaseMap Admin Console, you can register one or more SQL Servers inside your organization that will host your CaseMap or TextMap SQL case databases.

Once databases are registered, you can then set up the following users:

- CaseMap or TextMap client users who need access to SQL case databases
- CaseMap Admin Console users who can administer case databases and users

The CaseMap Admin Console is the only place you can create new CaseMap or TextMap SQL case databases. Once the case is created, you can assign it to users with local or Active Directory type authentication. Use the CaseMap or TextMap SQL Import Utility to migrate existing case files from the Access database format to the SQL database format.

#### **■\_To install the CaseMap Admin Console**

- 1. Click on the CMAdminSetup.exe file to launch the CaseMap Admin Console install utility.
- 2. When the InstallShield Wizard launches, click Next.



3. In the License Agreement box, select the I accept the terms of the license agreement.



- 4. Click the **Print** button to print a copy of the license agreement, then click **Next**.
- 5. In the **Information** dialog box, review the important installation information, then click **Next**.



6. In the **Default CaseMap Server** dialog box, type in the CaseMap Server in the **Name** 




- 7. In the **URL** field, type in the Server URL, then click **Next**.
- 8. In the **Choose Destination Location** dialog box, verify whether the default destination folder is the appropriate location.



The default folder is C:\Program Files\CaseSoft\CaseMap Admin Console.

Click the Browse button to change the destination folder and choose a different folder.

- 9. Click **Next** to continue.
- 10. In the **Start Copying Files** dialog box, review the current install settings, then click **Next**.



If you want to modify any settings, click the Back button.

11. In the InstallShield Wizard Complete dialog box, select the Launch the CaseMap SQL Admin Console check box.

Select the View the ReadMe File check box if you want to review the file.



#### 12. Click Finish.


The CaseMap Admin Console automatically launches and is ready for you to register a CaseMap Server.

13. In the Connect to CaseMap Server dialog box, select Local User.




- 14. In the **User Name** field, type *sysadmin*.
- 15. In the **Password** field, type in *password*.

- 16. Click Connect to continue.
- 17. In the CaseMap Admin Console, click the Click here to activate now hyperlink.




18. In the CaseMap Admin Console Software Activation dialog box, click Next to open the Enter your registration information dialog box.




19. In the **Registration Name** field, type in your user name for license registration.



- 20. In the **Registration ID** field, type in your registration ID.
- 21. In the **Product ID** field, type in the TextMap license number.
- 22. Click **Next** to continue.
- 23. In the **Read the LexisNexis License Agreement** dialog box, read the license agreement and then select the **Yes, I will abide by the LexisNexis License Agreement** check box.



- 24. Click **Next** to continue.
- 25. In the **How do you want to activate this product** dialog box, select the activation option you want to use.
  - Activate software online Use this option to activate online with an active internet connection.
  - Activate by web browser or phone Use this option if you received an activation key
    via email.
- 26. Click **Next** to continue.
- 27. In the **Summary of online activation transmission information** dialog box, review the license registration information.
- 28. Click **Finish** to complete the activation.
- 29. In the message box confirming CaseMap Admin Console activation, click **OK**.
- 30. In the CaseMap Admin Console, click the Connect button.



- 31. In the Connect to CaseMap Server dialog box, select Local User.
- 32. In the **User Name** field, type *sysadmin*.
- 33. In the **Password** field, type in *password*.
- 34. Click Connect to continue.

The CaseMap Admin Console now opens with a connection to the registered server.

You can now install the CaseMap or TextMap SQL Import Utility programs, if you plan on migrating existing local case files to the CaseMap Server.

#### Related Topics

About CaseMap Server

Installing CaseMap Server

Installing the CaseMap SQL Import Utility

Installing the TextMap SQL Import Utility

## Installing the CaseMap SQL Import Utility

## Installing the CaseMap SQL Import Utility

The CaseMap SQL Import Utility is designed to help you migrate pre-existing case files to CaseMap Server. This utility converts case files created in CaseMap v9.0 (or earlier) that are in

an Access database format and creates new SQL case files in a SQL Server database format. Each CaseMap case requires a distinct SQL Server database.

After you import an Access case file into a SQL Server database, use the CaseMap Admin Console to register the case database and then assign it to users. Once a case is migrated to CaseMap Server, it can no longer be accessed in previous versions of CaseMap.

## **■\_How to install the CaseMap SQL Import Utility**

- 1. Click on the **CMSQLImportSetup.exe** file to launch the CaseMap SQL Import utility.
- 2. When the import wizard launches, click Next.




In the License Agreement dialog box, review the license agreement and then select I accept the terms of the license agreement.


If you would like to print a copy of the license agreement at this time, click the Print button.



- 4. Click **Next** to continue.
- 5. In the **Information** dialog box, review installation information, then click **Next**.




6. In the **Choose Destination Location** dialog box, verify whether the default destination folder is the appropriate location.



The default folder is C:\Program Files\CaseSoft\CaseMap SQL Import\.

Click the Browse button to change the destination folder and choose a different folder.

- 7. Click **Next** to continue.
- 8. In the Start Copying Files dialog box, review the current install settings, then click Next.




If you want to modify any settings, click the Back button.

9. In the **Installshield Wizard Complete** dialog box, verify that the **Launch CaseMap SQL Import Utility** check box is selected.



- 10. Select the **View the ReadMe File** check box if you want to review the file at this time.
- 11. Click **Finish** to continue.
- 12. When the CaseMap 9 SQL Import Utility launches, click Close at this time.



When you are ready to migrate existing case files to the CaseMap Server, the LexisNexis CaseMap SQL Import Utility dialog box displays.

## Related Topics

About CaseMap Server

Installing CaseMap Server

About migrating case files

Migrating case files to CaseMap Server

Registering existing case files

Mapping case users

## Installing the TextMap SQL Import Utility

## Installing the TextMap SQL Import Utility

The TextMap SQL Import Utility is designed to help you migrate pre-existing case files to CaseMap Server. This utility converts cases created in TextMap v5.5 (or earlier) that are in an Access database format and creates new SQL cases in a SQL Server database format. Each TextMap case requires a distinct SQL Server database.

After you import an Access case into a SQL Server database, use the CaseMap Admin Console to register the case database and then assign it to users. Once a case is migrated to CaseMap Server, it can no longer be accessed in previous versions of TextMap.

### **■\_To install the TextMap SQL Import Utility**

- 1. Click on the **XMSQLImportSetup.exe** file to launch the TextMap SQL Import Utility.
- 2. When the import wizard launches, click **Next**.



- 3. In the **License Agreement** dialog box, review the license agreement and select **I accept** the terms of the license agreement.
- 4. Click the **Print** button to print a copy of the license agreement.



- 5. Click **Next** to continue.
- 6. In the **Information** dialog box, review installation information, then click **Next**.




7. In the **Choose Destination Location** dialog box, verify whether the default destination folder is the appropriate location.



The default folder is C:\Program Files\CaseSoft\TextMap SQL Import\

- 8. Click the **Browse** button to change the destination folder and choose a different folder.
- 9. Click **Next** to continue.
- 10. In the **Start Copying Files** dialog box, review the current install settings, then click **Next**.




If you want to modify any settings, click the Back button.

11. In the **Installshield Wizard Complete** dialog box, verify that the **Launch TextMap SQL Import Utility** check box is selected.



Select the View the ReadMe File check box if you want to view the file at this time.

- 12. Click **Finish** to continue.
- 13. When the **TextMap SQL Import Utility** launches, click **Close** at this time.



When you are ready to migrate existing case files to the CaseMap Server, the LexisNexis TextMap SQL Import Utility dialog box displays.

## Related Topics

About CaseMap Server
Installing CaseMap Server
About migrating case files
Registering existing case files
Mapping case users

## Migrating Case Files to CaseMap Server

## **About migrating cases**

Previous versions of CaseMap and TextMap cases are written to Microsoft® Access databases. CaseMap v9.0 and TextMap v6.0 also retain the option to create local case files in Access databases to save on a shared network folder. CaseMap Server allows you to import these files and convert them to SQL case databases managed in Microsoft SQL Server.

Migrating an existing case to CaseMap Server is two-step process. First you import the existing case using the CaseMap or TextMap SQL Import Utility. Next you register the imported SQL

case to the CaseMap Server using the CaseMap Admin Console. We recommend you set up CaseMap Server users with assigned roles in the CaseMap Admin Console before registering an imported SQL cases. This process allows you to map users from the CaseMap or TextMap Case Staff Member list to users defined in the CaseMap Admin Console after case registration succeeds. Once users are mapped they should automatically be assigned to the SQL case and able to open it in the client application. For more information, see Mapping case users.

Always backup copies of the local cases before you migrate them into CaseMap Server.

### **\_\_Learn** the key steps for successful case migration

Review the following for best practices in migrating case saved in Access databases and importing them into CaseMap Server.

#### **■** Involve your SQL database administrator

The first key to a successful migration is having your organization's SQL Server Database Administrator work with you in this process. Since each organization's needs are different, the SQL environment tends to be uniquely configured. Involving your SQL Database Administrator will help save you time and effort.

The CaseMap Technical Support team does not have knowledge of your SQL configuration and therefore, cannot answer your SQL questions. However, they can help you with your CaseMap, TextMap, and CaseMap Server / CaseMap Admin Console questions. When calling the support team, please make sure your SQL Database Administrator is on the call to answer SQL configuration questions from support.

#### **\_\_Follow steps outlined in this help topic**

The CaseMap and TextMap case migration process was tested by CaseMap developers. For a successful migration, be sure to follow these instructions as they are written and in the order they are described.

#### ■\_Learn why you should migrate local case files to CaseMap Server

Microsoft SQL Server is a widely available client/server relational database system. Microsoft SQL Server provides several benefits to CaseMap Server:

- Performs transactions and atomic operations for data safety and protection
- Runs at extremely high speeds
- Creates little or no disk fragmentation
- Allows for greater database size; not limited to 2 GB database size limits
- Allows for easy management
- ☑ The CaseMap v9.0 and TextMap v6.0 SQL options have been tested against Microsoft SQL Server 2005 and 2008.

Related Topics

Installing the SQL Import Utility
Migrating case files to CaseMap Server
Registering an existing case file
Mapping case users

## Migrating cases to CaseMap Server


Use the CaseMap or TextMap SQL Import Utility programs to migrate previous version case files to the CaseMap Server. During the import process, the utility converts a case in an Access database format to a SQL Server database format. It creates a brand new SQL case and copies all information from the old case into the new one. You will also have the option to create the new case on a specified server instead of using an existing one. Each CaseMap or TextMap case must be converted individually; there is no batch processing method. The utility program will install to C:\Program Files\CaseSoft\CaseMap\SQL Import. No local machine registry settings are required.

Once a case has been successfully imported to the CaseMap Server, the file extension on the previous version case is changed to ".001" to ensure that case staff can no longer open it in the client application. If a case file already exists with the same name and extension, the numbers will increment to ".002" and ".003" to ensure a unique name.

- Previous versions of CaseMap and TextMap are not used during the conversion process, so you can uninstall them at any time.
- ⚠ Once a case has been converted to a new version format, users can no longer access it using an older version of CaseMap or TextMap. We recommend that all users get new versions installed at the same time.

#### **■** How to migrate case files to CaseMap Server

- 1. Click on the CaseMap SQL Import icon to launch the CaseMap SQL Import Utility.
- 2. In the **CaseMap** or **TextMap Access Case to Import** area, click the **Browse** button to locate the case file you want to migrate to CaseMap Server.



- 3. In the **Server Name** field, type in the name of the SQL server you want to use.
- 4. In the **Authentication** drop-down list, select the authentication type you want to use: **Windows Authentication** or **SQL Server Authentication**.

If you are using SQL Server Authentication, type in your user name and password.

- 5. In the **SQL Server Case Database** area, select whether you want to create a new SQL server case database or use an existing empty SQL database.
- 6. In the **Database Name** field, type in the SQL database name.

The maximum limit for a case database name is 128 characters. As a general practice, it is best not to use spaces in the database name.

- 7. Click the **Import** button.
- 8. In the message box to verify the import, click **OK**.

The case file you imported is now ready to be registered in the CaseMap Admin Console. See To register existing SQL case files.

## Related Topics

About migrating case files
Registering existing case files
Mapping case users

## Testing installation

CaseMap and TextMap need to be installed before you can open the SQL case in either application.

## Testing installation involves:

- Opening the CaseMap Admin Console and connecting to the CaseMap Server
- Opening a SQL case in the CaseMap or TextMap client

## **■\_To test connectivity in the CaseMap Administration Console**

- 1. Launch the CaseMap Admin Console.
- In the Connect to CaseMap Server dialog box, type in or select the server you want to connect to in the Server Name field.



3. In the **Authentication** area, select the authentication method you want to use: **Windows Authentication** or **Local User**.


If you select Local User, type in the User Name and Password.

4. Click Connect.

You can now view the CaseMap Admin Console where you can register and publish case files, add users, etc.

## **■\_To open a SQL case file**

- 1. Launch either CaseMap or TextMap.
- 2. On the File menu, click Open SQL Case.
- 3. In the **Select a SQL Case to Open** dialog box, select the SQL case you want to use, then click **Open**.



4. Verify that the case name displays in the upper left corner of application's title bar.

- CaseMap If you can view case records in spreadsheets and open an attached file, the installation was successful.
- **TextMap** If you can view transcripts and open an attached file, the installation was successful.

Related Topics

Verifying connectivity

## Verifying connectivity

Reference the Connectivity Checklist to ensure that you have completed all necessary steps to ensure connectivity channels for SQL servers, SQL case files, and users.

## **■**\_To verify connectivity

Checklist: Connectivity					
	Task				
	Servers				
	Is CaseMap Server installed?				
	Is the CaseMap Administration Console installed?				
	Did you remember to set up an admin database and a valid system administrator account in SQL Management Studio first?				
	Case Files				
	Did you register your cases in the CaseMap Administration Console?				
	Did you associate your cases to SQL Servers so that CaseMap/TextMap can access it?				
	Have you implemented the necessary Web server address restrictions?				
	Users				
	Have you set up and enabled user accounts in the CaseMap Admin Console?				
	Does each user have a valid user ID and password, and does it match for Active				

# Checklist: Connectivity Task Directory? Have you assigned user accounts to roles and SQL case files? Do you have a CaseMap/TextMap license for each user who need to access case files? Have you installed CaseMap/TextMap locally for each user?

Related Topics

Testing installation

I	n	d	e	X
		$\mathbf{\omega}$	V	

# - A -

authentication types simple 7 Windows 7

# - C -

CaseMap command line parameters 31, 32 CaseMap Admin Console installing 34 CaseMap Server about migrating cases 59, 61 installing 20 migrating cases 61 7 system requirement v1.6 what's new CaseMap SQL Import Utility installing cases about migrating to CaseMap Server 59 migrating to CaseMap Server command line CaseMap parameters 31, 32 opening CaseMap SQL cases 32 32 opening TextMap SQL cases TextMap parameters configuring SQL Server for Casemap Server SQL Server for CaseMap templates 16 SQL Server Service Broker WebConfig file connectivity verifying 65

## - | -

installing
CaseMap Admin Console 34
CaseMap Server 20
CaseMap SQL Import Utility 45
testing 63

TextMap SQL Import Utility 52 verifying connectivity 65

# - L -

logon
automate CaseMap 31
automate TextMap 31

# - M -

migrating cases 61 about 59

# - S -

service broker
enabling in SQL Server 7

SQL Server
configuring for CaseMap Server 15
configuring for CaseMap templates 16
configuring Service Broker 16
enabling Service Broker 7

system requirements
CaseMap Server v1.6 7

## - T -

templates
configuring SQL Server 16
testing
installation 63
TextMap
command line parameters 31, 32
TextMap SQL Import Utility
installing 52

# - V -

verifying connectivity 65

# - W -

web servers
CaseMap Server 7

web servers
enable support for debugging 7
enable support for SSL 7
what's new
CaseMap Server 5